



---

## **Generally Accepted Agricultural and Management Practices for Cranberry Production**

---

**January 2014 – No Changes**

Michigan Commission of Agriculture  
& Rural Development

PO Box 30017  
Lansing, MI 48909

PH: (517) 284-5619  
[www.michigan.gov/mda](http://www.michigan.gov/mda)

**In the event of an agricultural pollution emergency such as a chemical/fertilizer spill, manure lagoon breach, etc., the Michigan Department of Agriculture & Rural Development and/or the Michigan Department of Environmental Quality should be contacted at the following emergency telephone numbers:**

**Michigan Department of Agriculture & Rural Development: (800) 405-0101  
Michigan Department of Environmental Quality: (800) 292-4706**

**If there is not an emergency, but you have questions on the Michigan Right To Farm Act or items concerning a farm operation, please contact the:**

**Michigan Department of Agriculture  
& Rural Development  
Right to Farm Program  
P.O. Box 30017  
Lansing, Michigan 48909  
(517) 284-5619  
(517) 335-3329 FAX  
(877) 632-1783**

|                                                                                                                                  |
|----------------------------------------------------------------------------------------------------------------------------------|
| <p>Authority: Act of 1981, as amended<br/>TOTAL NUMBER OF COPIES PRINTED: 25<br/>TOTAL COST: \$ 68.22 COST PER COPY: \$ 2.73</p> |
|----------------------------------------------------------------------------------------------------------------------------------|

# TABLE OF CONTENTS

|                                                               |    |
|---------------------------------------------------------------|----|
| PREFACE.....                                                  | i  |
| I. INTRODUCTION .....                                         | 1  |
| II. SITE SELECTION.....                                       | 2  |
| III. DESIGN & CONSTRUCTION OF CRANBERRY FARM OPERATIONS ..... | 4  |
| IV. WATER MANAGEMENT .....                                    | 5  |
| A. Irrigation .....                                           | 7  |
| B. Flooding.....                                              | 8  |
| V. NUTRIENT MANAGEMENT .....                                  | 9  |
| VI. INTEGRATED PEST MANAGEMENT (IPM).....                     | 10 |
| A. Pesticide Application and Handling .....                   | 10 |
| B. Weed Management .....                                      | 13 |
| C. Insect Management .....                                    | 14 |
| D. Disease Management.....                                    | 14 |
| E. Wildlife Management .....                                  | 16 |
| VII. POLLINATION                                              | 16 |
| VIII. PRUNING .....                                           | 16 |
| IX. HARVESTING .....                                          | 17 |
| X. SANDING .....                                              | 17 |
| XI. NEIGHBOR TO NEIGHBOR RELATIONS .....                      | 17 |
| APPENDIX I. References .....                                  | 19 |
| APPENDIX II. Agencies, Permits and Regulatory Programs .....  | 22 |
| APPENDIX III. Cranberry Site Requirements .....               | 28 |
| APPENDIX IV. Water Budget Data Sheet.....                     | 33 |

## PREFACE

The Michigan legislature passed into law the Michigan Right to Farm Act (PA 93 of 1981, as amended) which requires the establishment of Generally Accepted Agricultural and Management Practices (GAAMPs). These practices are written to provide uniform, statewide standards and acceptable management practices based on sound science. These practices can serve producers in the various sectors of the industry to compare or improve their own managerial routines. New scientific discoveries and changing economic conditions may require necessary revision of the practices.

The Generally Accepted Agricultural and Management Practices that have been developed are the following:

- 1) 1988 Manure Management and Utilization
- 2) 1991 Pesticide Utilization and Pest Control
- 3) 1993 Nutrient Utilization
- 4) 1995 Care of Farm Animals
- 5) 1996 Cranberry Production
- 6) 2000 Site Selection and Odor Control for New and Expanding Livestock Production Facilities
- 7) 2003 Irrigation Water Use
- 8) 2010 Farm Markets

These practices were developed with industry, university and multi-governmental agency input. As agricultural operations continue to change, new practices may be developed to address the concerns of the neighboring community. Agricultural producers who voluntarily follow these practices are provided protection from public or private nuisance litigation under the Right to Farm Act.

This GAAMP does not apply in municipalities with a population of 100,000 or more in which a zoning ordinance has been enacted to allow for agriculture provided that the ordinance designates existing agricultural operations present prior to the ordinance's adoption as legal non-conforming uses as identified by the Right to Farm Act for purposes of scale and type of agricultural use.

The website for the GAAMPs is <http://www.michigan.gov/gaamps>.

## I. - INTRODUCTION

Michigan has the climate, soils, and processing infrastructure necessary to support a cranberry industry. High market demand and price have stimulated interest in cranberry production outside traditional cranberry producing areas. Several individuals have recently begun growing cranberries in Michigan; numerous others are considering this crop, and Michigan cranberry production is expected to increase over the next few years.

The cranberry plant is a wetland crop species (an obligate hydrophyte) that is grown commercially in natural or artificial wetlands managed for crop production. Since the production of cranberries is a water dependent activity, many unique cultural and management practices have been developed for their production. Five to ten acre-feet of water may be needed annually per acre of cranberry bed. Farming within a wetland environment presents considerable potential for adversely affecting existing natural resources or the function of those resources. Cranberry producers need to minimize these risks by utilizing environmentally sensitive and sound management practices.

Cranberries are commercially produced in the mild marine climate of western Oregon and Washington, the moderate climate of Massachusetts, New Jersey, and Maine, and the harsh continental climate of Wisconsin. Some management practices differ from one region to another to reflect these climatic differences. For example, winter flooding and ice cover is a necessity in Wisconsin, but no winter protection is required in Oregon and Washington. Some characteristics of Michigan's climate fall between these extremes. Therefore, Michigan growers may eventually find that management practices employed in other states may not be completely suited to all areas of Michigan. Recommendations for commercial cranberry production in Michigan will likely change as the industry develops and technologies change.

These current Generally Accepted Agricultural and Management Practices (GAAMPs) were developed as a result of a Memorandum of Agreement between the Michigan Department of Agriculture & Rural Development (MDARD) and the Michigan Department of Environmental Quality (MDEQ). These agencies have a mutual interest in the development of a viable cranberry industry in Michigan, and are dedicated to protecting environmental quality. The GAAMPs are intended to provide technical and regulatory guidance that is economically viable and environmentally sensitive. Farm operations voluntarily following these GAAMPs will be provided nuisance litigation protection and other provisions pursuant to the Michigan Right to Farm Act, PA 93 of 1981 (RTFA), as amended (MRFA). The Michigan Commission of Agriculture & Rural Development (Commission) has the responsibility to define GAAMPs under the RTFA and has identified the need for these GAAMPs to address the unique issues relative to cranberry production. GAAMPs will be reviewed annually and revised by the Commission when necessary.

## II. - SITE SELECTION

Nearly all regions of Michigan meet the climatic requirements of cranberries. However, it is necessary that cranberry production operations be located in sites with proper soil and hydrologic conditions for successful commercial production. These conditions will directly influence the design, construction and operational costs of the farming operation. Because cranberries require the existence or establishment of wetland conditions and large quantities of water, certain regulatory requirements may also need to be met for a specific site. Site selection, farm design, construction of beds and associated facilities, and operational activities must take into account the federal, state, and local regulatory requirements. The presence of regulated wetlands and water bodies within, or adjacent to, a site considered for cranberry production, and possible permit requirements regarding wetland alterations or impacts to bodies of water should be considered, and may influence site selection, as well as farm design and placement and construction of cranberry beds, reservoirs, dikes, and associated management facilities. A cranberry site review team composed of MDARD, MDEQ, and MSU staff can provide technical assistance in determining the suitability of potential cranberry sites. Contact Erik Johnson from the MDARD (231 357-4323, [johnsone9@michigan.gov](mailto:johnsone9@michigan.gov)) to request assistance.

### **Sites need to meet the soil and water requirements of cranberries.**

Cranberries require a growing media of sand or organic soil with an acidic pH (below 5.5). Higher pH materials are suitable if pH can be reduced economically. A nearby source of suitable sand is needed for construction and future sanding practices. Hydrologic and soil characteristics should provide the capacity to maintain the water table at or near the bed surface. Preferred sites also have minimal slope, since flat areas generally require less earth moving to develop. A ready supply of water is needed, which is physically and legally usable. Water with an acidic pH is preferred. More detailed cranberry site selection considerations are provided in Appendix III. The USDA Natural Resources and Conservation Service (NRCS) can provide copies of local soil surveys and other soils data.

### **Regulatory requirements must be met.**

Site selection, farm design, construction and operational activities need to consider all applicable federal, state and local regulatory requirements, and any tribal laws and regulations. Prior to establishing a cranberry production site, producers should consult with the Water Resources Division (WRD, formerly the Land and Water Management Division) of MDEQ and all other appropriate agencies to determine if any permits are required. All required permits need to be obtained prior to initiation of any regulated activities, such as, construction of cranberry beds and associated facilities. Regulatory programs are described in Appendix II. Early contact will advance the identification of possible permit requirements and the application review process. The MDARD Environmental Stewardship Division and Michigan State University Extension may also be helpful in identifying potential sites.

The selection of a site for growing cranberries that recognizes environmental concerns along with proper farm design and operation will ease compliance with applicable regulatory requirements. A qualified environmental consultant who is familiar with regulatory requirements may be helpful in the site selection and design process. The grower or their consultant should contact the regulatory agencies in the initial stages of site selection and design of the farm operation.

The following information on site selection is provided to help identify locations that either do not require a wetland or other state permit(s) for development, or represent sites that are more acceptable under permit review criteria.

**A. Sites that are considered either upland sites or prior wetland areas that have previously been drained for agricultural use and no longer meet the regulatory definition of a wetland. These are the more desirable sites for cranberry development and do not require a wetland permit for bed development but may require other local, state, or federal permits.** In a number of regions in Michigan, former wetland areas with suitable soils have been drained for agricultural use and may be suitable for cranberry growing if steps are taken to restore the high water table (e.g. placement of water control structures on drainage outlets) and other criteria are met.

**B. Sites having soils which have been drained for agricultural use but which do meet the state and federal definitions of a wetland. These sites require permits for construction of cranberry beds and associated facilities. However, permits will likely be issued unless other resources would be adversely impacted by the proposed conversion.** For sites which are still technically a wetland, but which have reduced wetland values due to past or current agricultural drainage, MDEQ wetland review criteria will not be more stringent than federal permit review requirements. The applicant will need to minimize impacts on wetlands and associated resources, and should locate support facilities within upland areas where feasible.

**C. Permits are required for construction of cranberry beds in natural, undisturbed wetlands.** Permit review requirements will be consistent with federal programs regarding construction of cranberry beds in natural, undisturbed wetlands, and will weigh the impacts and benefits of the proposed project.

MDEQ will evaluate applications for permits involving potential sites for cranberry development on a case by case basis, including sites that do not clearly meet the above criteria. As required by the 2009 amendments to Part 303, Wetland Protection of the Natural Resources and Environmental Protection Act, PA 451 of 1994, as amended, the

Commission in consultation with the MDEQ is to prepare informational maps that identify a total of 5000 acres of land in Michigan considered suitable for cranberry production. When completed, these informational maps will be made available to the public on the MDEQ website.

### **III. - DESIGN AND CONSTRUCTION OF CRANBERRY FARM OPERATIONS**

An economically feasible and environmentally sound cranberry farm operation depends on appropriate planning for facility design and construction activities. The NRCS provides useful information on most aspects of design and construction for erosion and sedimentation control. The Conservation Practice Standards and Specifications are contained in the NRCS electronic Field Office Technical Guide (eFOTG), available at <http://www.nrcs.usda.gov/technical/efotg>. Additional technical assistance may also be obtained from local NRCS or conservation district offices or private sector professional engineering firms or technical service providers.

#### **Cranberry beds need to meet the growth requirements of the plants and facilitate management.**

Arrangement, dimensions, and elevations of beds depend on the topography and other site characteristics. Construction procedures are site specific, but some general steps are followed. To construct cranberry beds, the surface soil is usually removed and, if suitable, often used to build dikes and roads. In most cases, clean sand is spread over the bed, and the surface is leveled. Drainage ditches are usually dug around the perimeter of the beds. Subsurface (tile) drain and pumping plant for water control may also be installed.

#### **Water management facilities need to meet the annual water requirements.**

The large quantity withdrawal of either surface and/or groundwater statutorily requires the property owner or their authorized agent to use the MDEQ's online (<http://www.miwwat.org>) water withdrawal assessment tool to evaluate and determine if the proposed withdrawal is acceptable or requires a site specific review by the WRD of the MDEQ. The tool is intended to assist in water use planning decisions and to prevent adverse resource impacts to surface waters that can result from the withdrawal of too much water. The registration of an acceptable large quantity withdrawal (LQD) may be completed using the online tool. If the tool indicates that the LQD may cause an adverse resource impact, the property owner may submit a request to the MDEQ for a site specific review.

A detailed water budget should be calculated to help insure an adequate and timely water supply. An example of a water budget evaluation is provided in Appendix IV. Ponds are usually constructed to serve as water reservoirs. Wells may supplement the water supply. Various drainage ditches, dikes, canals, bulkheads, and irrigation and drainage systems are usually installed to move water to and away from beds.



All new cranberry growers should consider designs that allow for water recycling. These systems are referred to as "closed systems" because surface runoff and drainage water from the beds is retained and later reused. Properly managed closed systems can provide a higher level of environmental protection.

Closed systems usually have an upper reservoir that serves as the water source and a lower recovery reservoir. It is desirable to have the beds at a lower elevation than the water source. Water is temporarily stored in the down slope reservoir where potentially nutrient-bearing sediments are trapped and some breakdown of pesticides occurs. Generally, water levels in the down slope reservoir should be kept low when pesticides are applied. Pesticide residues moving out of beds in the drain water can then be retained and degraded in the down slope reservoir. This will help to protect groundwater and surface water quality. This water can also be pumped back into the beds or an upslope reservoir and reused. Recycling water in this manner reduces the water capacity required in the upslope reservoir and the need for water from other sources. In sites where a large amount of surface water runoff from higher land may inundate the bed area, diversion ditches may channel excess water from the beds.

Cranberry operations that divert surface water runoff, and drainage water from beds to streams or other surface water bodies (and do not collect and recycle water) are called "open systems". After a pesticide application, any water in the treated area needs to be held for no less than the time indicated on the pesticide labels before it can be released. Open systems have a greater potential than closed systems to adversely affect the environment. Proper design and management of an open system should minimize the potential for adverse environmental impacts.

#### **Control soil erosion and sedimentation during construction.**

Soil erosion control is an important component of agricultural non-point source pollution prevention programs, because soil itself can be a pollutant and may be a carrier of pollutants, such as adsorbed pesticides and nutrients. Avoid disturbing soil during heavy rain or wind storms. Blowing dust and wind erosion can be reduced by sprinkling water on dry soil or sand. Excavated sand should be stockpiled away from open water. Consider lining stream and ditch banks with silt fences to prevent sedimentation. Grass or vegetation should be established on roadways, dike roads, etc. as soon as possible to reduce the likelihood of soil erosion.

### **IV. - WATER MANAGEMENT**

Water is essential to cranberry production; it is used for spring reflow, frost protection, irrigation, harvest, and winter protection. Depending on the site, water may be obtained from or discharged into sources such as lakes, rivers, streams, drains, or reservoirs, as allowed by common law water rights and subject to obtaining necessary state permits.

Water movement in and out of beds is controlled by a system of dikes and ditches. Excessive water may be drained or pumped to various water recovery or release areas.

**Dikes, ditches, reservoirs and flumes should be maintained.**

Dikes control water movement and support production equipment. Since wind, water, and burrowing animals deteriorate dikes, maintenance and upgrading are essential for efficient water containment and movement, and safe vehicle passage. Burrowing animals are the primary cause of dike failure and must be controlled. Establish grass or other vegetation on dikes and ditch banks to stabilize the soil. However, vegetation should be mowed so that it does not produce seed and increase weed pressure in the beds. Ditch bank erosion commonly occurs when saturated, unstable soil materials are subject to high velocity water flow. Erosion can be reduced by installing geofabric or geogrid material, rock cover, or riprap to unstable embankments and down gradient sides of flumes, and by lowering water levels in ditches to improve bank stability during periods when the soil is wet, because saturated soil has little strength. Designed soil erosion control practices, such as those identified above, can be requested from the NRCS and the local conservation district or technical service providers.

Private ditches and waterways need to be free of excessive vegetation and sedimentation that can impede drainage. If beds have adequate soil drainage, some live aquatic vegetation left in the ditches during the growing season may help filter nutrients and pesticides from the water. In this case, delay cleaning ditches and waterways until later in the season to take full advantage of this filtering action.

When cleaning private ditches, ponds, or reservoirs, be careful not to undercut ditch banks or to dig ditches too deep, since undercutting leads to instability and bank failure. If sediment being dredged from ditches has a fine texture, a silt fence is effective to capture sediments before they move offsite. Cleaning ditches from the point most distant from the flume (moving towards the flume) will enhance sediment settling. Dispose of spoils on established dikes or other upland areas. Allow ample time for excess water to drain out of dredged sediments before being moved. Use silt fences to keep sediments contained. Growers should employ all reasonable sediment control and removal techniques to receive and cleanse waters exiting the bed. Growers should also consider diverting sediment-charged water to holding ponds to allow settling of solids.

Worn or damaged flume or bulkhead boards should be replaced regularly to prevent the escape of ditch or flood water. Keep boards free of debris and consider using rubber gasket strips on channel guides or a tension activated tie down system to decrease leakage. Consider locking flume or bulkhead boards in place.

**Reduce ditch water levels as much as possible before applying nutrients and pesticides.**

Lower water levels in ditches before applications to allow for absorption of nutrients and pesticides into ditch sediment and vegetation, and increase water holding time.

**Adequate drainage is needed in all beds.**

Proper soil drainage is needed for healthy vines. Healthy vines may require less fungicide because they are less prone to diseases such as root rot. Drainage may be improved by installing surface drainage, main or laterals or subsurface (tile) drains, or by winter sanding.

**Anticipate weather.**

Heavy rainfall can wash nutrients, especially nitrogen and pesticides off the target area. Follow weather forecasts and halt fertilizer and pesticide applications when rainstorms are forecasted or frost protection is required.

**A. IRRIGATION**

Sprinkler irrigation is essential for cranberry culture to protect plants from spring and fall frost damage, supply water during the growing season, and apply nutrients and pesticides. To perform these functions effectively, irrigation systems should be engineered and maintained to provide maximum water application uniformity. The current Generally Accepted Agricultural and Management Practices for Irrigation Water Use (MDARD) provide useful general guidance on irrigation use.

**Irrigation systems should be designed for uniform water application.**

Irrigation systems should deliver uniform application rates of 0.1 to 0.15 inches per hour. To optimize uniformity, reduce system pressure losses by protecting pipes from dents and limit the number of 90 degree elbows. Reduce plugging by installing clean out plugs at lateral ends and a strainer basket on the intake pipe. Secure risers to a vertical stake to limit wobble. Straight, stationary risers provide more uniform water application.

**Irrigation equipment should be maintained in effective operating condition.**

Follow manufacturer recommendations for pump, valve, and sprinkler head maintenance. Inadequate maintenance can result in breakdowns at critical times, reduced system uniformity, and inappropriate application rates. Precautions should be taken to prevent fuel leaks or spills.

**Irrigation application rates and uniformity should be tested periodically.**

Irrigation system uniformity should be tested regularly. Systems with low uniformity cause some areas to receive adequate water while others receive too little or too much. Coefficient of Uniformity (CU) of less than 60 percent indicates the system needs updating or was not properly installed. The NRCS recommends a CU of 85 percent, an attainable goal using current technology. Uniformity may be affected by sprinkler rotation speed, pattern type and spacing (closer spacings give higher uniformities), nozzle pressure, wear, and size, different trajectory angles resulting from leaning risers, friction losses in laterals, different sprinkler elevations, and wind. Data collected from an irrigation uniformity test can be used to calculate the

system's irrigation rate, and modifications can be made by changing operating pressure or nozzle size.

**Irrigation should be applied at appropriate rates and intervals.**

Newly set plants should receive frequent, light applications of water for the first two weeks or until roots form. To promote deeper rooting, irrigate newly planted beds less frequently but longer after plants become established. Established beds require one to two inches of water per week. Irrigation rates should be reduced to reflect rainfall received in lieu of irrigation water. Apply up to 0.5 inches per irrigation event.

Irrigation should be used to cool plants when ambient air temperatures reach 85°F or higher. Cool plants by irrigating for about one hour to thoroughly wet the plants and soil surface. Irrigate again when temperatures rise to 85°F. Drain surface pipes between irrigations to prevent scalding caused by hot water in pipes.

When irrigating for frost control, monitor both temperature and growth stage, since lethal temperatures vary with growth stage. Begin irrigating when temperatures at bed level are one to two degrees above the critical temperature, and stop irrigating when temperatures rise safely above the critical temperature. Effective frost protection requires irrigation rates of at least 0.1 inches per hour. This rate protects buds and fruit to a temperature of 20°F (under wind conditions of 0 to 1 mph). Sprinklers should rotate at least once per minute to provide frost protection.

## **B. FLOODING**

Cranberry beds are flooded in the fall to harvest berries following dry harvest to remove trash and debris, during the winter to protect plants from cold injury and in the spring to control some pests, remove frost from the soil and protect plants from severe freezes.

**Harvest.**

Hold harvest flood water in beds for at least one day, and then slowly pump or drain the water from the beds.

**Winter flooding.**

The cranberry is an evergreen plant that can be damaged by cold and fluctuating temperatures. Beds are usually flooded in early winter so that ice covers the plants and protects them from cold, windy weather. This ice layer also makes it possible to apply sand.

Winter flood water should be applied when the surface layer of soil has frozen. The water needs to come from a surface source rather than ground water. Having the ground frozen decreases the potential of losing flood water through seepage. Using surface water that is already near freezing also reduces the chance of removing

frost from the ground. The winter flood water should be applied as quickly as possible without causing soil erosion. Fast flooding reduces the chance of the wave action of the water pulling out the plants.

Drain flood water slowly to minimize water fluctuations and sedimentation in water recovery or release areas.

## V. - NUTRIENT MANAGEMENT

Cranberry beds require fertilizer applications to produce economic yields. However, nutrients such as nitrogen (N) and phosphorus (P) can harm water quality if not managed properly. Excessive use of fertilizers can injure cranberry plants and reduce yields. Refer to the GAAMPs for Nutrient Utilization, Michigan Commission of Agriculture & Rural Development, for general information on how fertilizers should be handled and used to minimize environmental impacts. Refer to university recommendations for guidance on fertilization practices.

### **Nutrient use should be based on plant performance, tissue analysis, and soil test results.**

Beds on organic soils may require as little as 10 lbs. N per acre per year, whereas those on sandy soils may need as much as 60 lbs. per acre. Determine the appropriate rate for specific beds based on vine growth and yields, tissue N levels, and previous fertilization practices. Refer to the Compendium of Blueberry and Cranberry Diseases (APS Press) for descriptions of nutrient deficiency and toxicity symptoms.

### **Plan fertilizer applications to correspond with crop demand.**

Fertilizers containing N and P should be applied between bud break and late August, when plants are most able to utilize nutrients. This reduces chances of N or P loss to the environment. Fall or early spring applications of fertilizer increase the risk of nutrient losses through leaching and should be avoided. Potential for leaching is greatest on coarse textured soils. Lower rates applied when the plants are able to use the nutrients reduce runoff potential and increase nutrient efficiency.

### **Ammonium forms of N should be used.**

Cranberries prefer ammonium-N over the nitrate form. Ammonium-N adsorbs to clay and organic matter in the soil, so it is less mobile than nitrate-N, and less prone to leaching.

### **Fertilizer application equipment should be calibrated.**

Fertilizer is applied to cranberry beds with spreaders or booms, airplanes, or helicopters, or through irrigations systems. All application equipment should be calibrated according to the manufacturer's recommendations to insure the proper amount of fertilizer is applied.

**Direct application of fertilizers to open water on cranberry beds should be minimized.**

When applying fertilizer to cranberry beds through irrigation systems, use part-circle sprinklers or sprinkler guards to minimize fertilizer applications to open water on cranberry beds, which can result in off-site movement.

**Soil pH should be maintained in the proper range.**

Nutrient utilization and plant growth are optimized when soil pH is between 4.0 and 5.5. Additions of sulfur may be needed to keep soil pH sufficiently low. Sulfuric acid may need to be added to irrigation or flood water that is high in alkalinity. Water discharged off the site should be in compliance with water quality standards. Safety precautions should be followed to prevent inadvertent contact with concentrated sulfuric acid.

## **VI. - INTEGRATED PEST MANAGEMENT (IPM)**

Commercial cranberry production requires management of insect pests, diseases, and weeds. IPM integrates biological, cultural, and chemical control practices to manage these production problems. IPM requires knowledge of pest life cycles and identifying characteristics, and an understanding of all available control options. By scouting cranberry beds and understanding pest biology and control options, growers are able to make appropriate pest management choices. Useful references may be found in Appendix I.

### **A. PESTICIDE APPLICATIONS AND HANDLING**

The current version of the GAAMPs for Pesticide Utilization and Pest Control, Michigan Commission of Agriculture & Rural Development, provides general guidance on agricultural pesticide use. These GAAMPs describe information on applicator certification, application equipment, methods and record keeping, pesticide handling and safety, disposal of excess spray mixtures, and unused pesticides and pesticide containers. Instructions on the pesticide label must be followed. They are the law. Pesticide applicator certification is required to purchase or apply restricted use pesticides. Certification is recommended for all persons applying pesticides. Pesticide users also must comply with the Federal Worker Protection Standards. Keeping accurate records of pesticide applications is essential for farm planning and performance evaluation. Some considerations in pesticide use that are specific for cranberries are discussed below.

**Understand alternatives to pesticide, which are available for the crop to be grown.**

The options for pest management in agricultural crops include non-chemical and chemical control. The pesticide user should consider alternatives and make

conscious decisions concerning pesticide use that evaluate potential site contamination, pest management, and economics of use. Non-chemical means of control include sanding, flooding, and biological controls including Bts, nematodes, etc.

**Calibrate application equipment properly.**

Proper calibration ensures equipment is delivering the correct amount of pesticide and applying it uniformly over the target area. Over-application creates needless risks to water resources and increases economic inputs and must be avoided. Under-application will result in inadequate control and economic loss.

**Develop a plan to follow in case of pesticide emergencies.**

Pesticide applicators should develop an emergency plan that lists actions to take and persons to contact in case of pesticide poisoning, spill, fire, or other accidents. Compliance with SARA Title III regulations is described in MSU Extension Bulletin E-2175.

**Keep pesticide applications out of surface waters by avoiding over-spray and drift.**

Prevent non-target application by shutting off sprayer when boom or mist blower crosses ditches or waterways. In most cases, label language prohibits application directly to open or surface waters. Follow label guidelines regarding wind speeds and equipment requirements in order to direct applications to the target. Application of pesticides during excessive wind (greater than five mph) causes unnecessary non-target application, reduces uniformity of the application, and reduces pesticide efficacy. Use anti-drift agents when appropriate. Regardless of application method, every effort should be made to keep pesticides confined to the bed and out of open or running water.

**Consider the vulnerability of water and other natural resources when making pest management decisions.**

The risk of inadvertent contamination of surface and groundwater resources differs for each farm. Pesticide users should include the risk to water resources as criteria of pest management decisions. The potential for contaminating groundwater is influenced by soil characteristics, depth and type of bedrock, and depth to the water table.

**Apply pesticides only as needed.**

When making pesticide applications, use the lowest effective rate. IPM allows for better management of pest problems. IPM can provide information on pest populations that allows spot treatments and improves timing of treatments. These two strategies can lead to a reduction in overall use due to increased efficacy and earlier control.

**Hold water containing pesticide residues for required or recommended times.**

Holding water in ditches allows for degradation and dissipation of pesticide residues. All waters in contact with the beds must be retained for the length of time required by the label and, ideally, held as long as practical to allow maximum degradation. Low water levels in ditches prior to application increases the water holding capacity of a bed.

**When aerial applications of pesticides are made on beds adjacent to or near a road or highway, consider using flag people to control or stop traffic flow during application.**

Inadvertently spraying pesticides on motor vehicles traveling on public roads is illegal and will initiate an investigation by the MDARD. Repeated occurrences could jeopardize continued availability of aerial pesticide applications. Posting of flag people to stop traffic along both approaches to the bed, prior to a pesticide application, will minimize the incidence of accidental exposure.

**When chemigating, make sure your system complies with federal and state laws.**

Label instructions must be followed when applying chemicals through the irrigation system (chemigation). Pay particular attention to application, reentry, pre-harvest and water retention times. If an irrigation system is used to apply pesticides, it must be fitted with a check valve, low pressure drain, vacuum breaker, low pressure shutoff switch, and injection port on the discharge side of the pump. Pesticides cannot be legally introduced into an irrigation system through the suction side of the pump. Refer to MSU Extension Bulletin 2099 for chemigation techniques and compliance rules. Determine the amount of time it takes a pesticide to travel through an irrigation system by injecting a dye into the system and monitoring its flow through the system with a stopwatch. This information is necessary to optimize pesticide performance. Pesticide will be left in the irrigation lines if the system is operated for less than the injection time, whereas running the system for too much time can result in pesticide being washed off the target area. Pesticide injection times of greater than ten minutes may adversely affect pesticide performance.

Check your irrigation system and property before every pesticide application.

Effective insect and disease control requires that the irrigation system performs satisfactorily. Confirm that main and lateral lines are not leaking and sprinkler nozzles are not plugged. Inspect the entire property to insure people or animals are not present at or near the pesticide application area. These procedures should be followed if the pesticides are applied by the grower or custom applicator. Inspect property after application to be sure all signs are properly posted and that there are no people or animals present or near the application site.



Chemigation should only be practiced when uniformity, as measured by Coefficient of Uniformity Test, exceeds 60 percent. Non-uniform application of pesticides can pose a serious environmental and food safety risk. Optimize irrigation system performance before using chemigation as a pesticide application technique. Use of part-circle sprinklers can be effective in keeping pesticides out of surface water and off dikes and travel lanes.

## **B. WEED MANAGEMENT**

Weeds in cranberry beds need to be managed. Effective weed control usually requires the integrated use of chemical and cultural strategies.

### **Scout for weeds.**

Weeds must be identified correctly in order to choose effective control measures. Several references listed at the end of these GAAMPs may be useful in identifying common weed species. In scouting, note the species, infestation severity, and location for future management decisions.

### **Use cultural practices where possible.**

Sanding and hand weeding can be effective weed management practices, especially in young plantings. Weed competition can be reduced by maintaining a low soil pH and encouraging healthy, vigorous vine growth that competes with weeds.

### **Use herbicides judiciously and always according to label instructions.**

Refer to university recommendations for specific suggestions on herbicide use. Always read and follow label instructions and use the lowest effective rates. Consider bed conditions such as soil composition, weed pressure and species, and drainage in choosing herbicides and rates. Spot treat if possible. Use markers or dyes to double check where you have already applied herbicides. Apply herbicides when vines and beds are dry. Splitting applications of granular herbicides may result in better control and minimize off-site movement.

Herbicide application equipment should be calibrated annually or each time a new material is applied. Check for changes in output due to equipment wear. Ground equipment is the preferred method of granular application, providing uniform coverage and minimal off-target exposure. Understand the leaching potential of each herbicide.

### **Prevent weeds from establishing in beds.**

Start with a clean, weed free bed. Control weeds when they first appear and before they spread. For example, hand wipe or pull brambles, tree seedlings, and dodder. Mow dikes and other adjacent areas to prevent weeds and weed seeds from moving into the bed.

## C. INSECT MANAGEMENT

Various insect pests may infest cranberry beds and require chemical and cultural control practices in order to avoid crop losses.

### **Avoid resistance.**

Repeated use of the same insecticide can rapidly select for resistance in certain insects and should be avoided by rotating insecticides used, integrating biological and cultural controls into management programs, and reducing insecticidal inputs to a minimum. Spot treat whenever possible.

### **Predict insect infestations to increase scouting efficiency.**

Heat unit accumulation models, migration prediction systems, pheromone and light trapping networks, and other predictive technologies should be used to maximize scouting efficiency, optimize timing of applications and improve pesticide decisions made by growers.

### **Protect natural controls.**

Natural predators and parasites play an important role in regulating pest insects. Their role should be enhanced wherever possible by minimizing exposure of beneficial insects to disruptive insecticidal treatments. Beneficial insect populations can be encouraged by conservation and reduced reliance on chemical control practices.

### **Adopt biological controls that are effective alternatives to insecticides.**

In cases where biological controls play a major role in regulation of pests in natural systems, such controls should be utilized. When natural controls are present, these should be encouraged and protected to achieve maximum potential. In the absence of natural controls, parasites or predators may sometimes be introduced and successfully established.

### **Consider the environmental risk when selecting insecticides.**

When insecticide applications are needed, select products that will provide control and minimize the potential for adverse environmental effects. Factors such as risk to non-target organisms, toxicity, persistence and potential for contamination of ground and surface water should be considered. If the potential exists for adverse aquatic effects, consider less toxic compounds.

## D. DISEASE MANAGEMENT

Cranberry diseases can be best managed by integrating cultural and chemical control practices. The susceptibility of cranberry vines to disease is often associated with the overall plant health and vigor, as well as environmental and cultural conditions. The strategies and practices below may help increase disease

resistance in the plant and make conditions in the bed less favorable for disease development. Optimum integration of several of these practices, where appropriate, will help manage diseases with minimal chemical input and environmental impact in an economically feasible and profitable way.

**Growers should be familiar with disease symptoms and pathogen biology.**

Refer to references in Appendix I for information on cranberry disease diagnosis and life cycles. Beds should be scouted regularly to determine disease presence and severity. Make sure the disease is correctly diagnosed before deciding on control measures.

**Optimize nutrient practices to increase disease resistance in plants.**

Plants that are stressed by inadequate nutrition may be more susceptible to some diseases. Also, excessive nitrogen can result in rank vine growth that is susceptible to pathogen attack. Overgrowth often results in increased humidity and extended vine wetness, which encourages pathogen activity.

**Adopt cultural disease control practices.**

Cultural practices aimed at removing or disrupting pathogens should be employed when feasible. The practice of sanding buries pathogen infested duff and proper disposal of trash piles following harvest removes inoculum. In some regions, spring floods can effectively disrupt pathogen activity. New beds should be planted with vines from healthy beds or plug plants, using disease tolerant varieties where practical. Reduce soil, water, and plant material movement from diseased beds to non-infested beds in order to limit the spread of pathogens.

Plants stressed by too little water, over watering, and/or poor drainage may be more susceptible to pathogen attack and disease development. Practices that improve drainage where needed and minimize the time during the growing season when plants are wet, should be considered. Optimizing irrigation system uniformity will improve drought management, reduce freeze damage due to inadequate frost protection, and improve disease control where chemigation is practiced.

**Optimize uniformity of fungicide applications.**

The degree of disease management with fungicides is highly dependent on uniform application coverage. Enhance disease management by making cost effective improvements to application systems where needed, to optimize uniformity of coverage across the bed and on the target plant parts. For each chemical application systems used to apply fungicides, determine and use the optimum amount of water, pressure, injection timing, etc., needed to obtain desired product application.

**Optimize number and timing of fungicide applications.**

For most fungal diseases in cranberries, control is best or only obtained by preventing initial attack by the pathogen. Understand life cycles and the influences of weather, and apply protective fungicides only during infection periods. Complete control is not always needed or cost effective, so only make applications when the fungicide provides substantial economic benefit.

**Choose fungicide and formulation best suited to the current target problem.**

A steady increase or a noticeable change in disease problems over a few years may indicate a need to change fungicides or rates to better manage fungal populations. Pathogen populations and activity change from year to year for many different reasons, so fungicides may lose effectiveness. Choose the fungicide that will provide adequate control but is also the most cost effective and environmentally compatible. Choose formulations best suited for your application system. Use less persistent, but effective, fungicides late in the growing season to reduce fungicide residues on fruit. Use the lowest effective fungicide rate.

**E. WILDLIFE MANAGEMENT**

Gates and fencing may be needed to control access to cranberry operations and reduce deer damage and, in some cases, vandalism and theft by humans. Muskrats and other burrowing animals need to be monitored and controlled, since they damage dikes and roads. Contact the Michigan Department of Natural Resources (DNRE) Wildlife Division for regulations regarding trapping of nuisance animals. Noisemakers, projectiles and other scare devices may be used to minimize damage from all forms of wildlife, as warranted.

**VII. - POLLINATION**

Cranberries require bees for pollination. During the bloom period (mid-June to mid-July), honey bee hives are placed in the production area. One or more hives should be used per acre of cranberries. Insecticides that may harm bees should not be applied during bloom. Bumble bees may also be used for pollination.

**VIII. - PRUNING**

Vines should be mechanically pruned periodically to remove excessive growth and encourage upright production. Vines removed during pruning may be sold or used to establish new beds or renovate less productive beds.

## **IX. - HARVESTING**

Cranberries should be harvested when they have met the proper maturity indices (primarily color). Harvest will be from late September through October.

### **Flood harvest.**

Berries to be sold for processing are generally harvested by flooding the beds and mechanically removing the berries. The berries float and are corralled to one side of the bed and removed by elevators or suction pumps. When flooding for harvest, flood as quickly as possible without causing bed erosion. Harvesters should contain food grade hydraulic oil and each harvester must have an oil containment kit and the operator instructed on how to properly use it. Flood water should be pumped or drained slowly after harvest is complete. Trash collected from beds at harvest should be removed from the planting area to reduce disease inoculum.

### **Dry harvest.**

Berries sold for fresh consumption are generally dry harvested. Typically, berries are mechanically removed from the plants, placed in bins and removed from the bed for cleaning and storage. Dry harvested beds may be flooded after the berries are removed so the trash can be floated off. This sanitary practice removes diseased fruit and vegetation, and reduces the disease pressure the following season. All flood water should be released slowly to minimize erosion.

## **X. - SANDING**

### **Cranberry beds should be sanded every two to five years.**

Sanding encourages growth and suppresses some insect pests and diseases. Sanding on top of the ice is preferred to applying sand in water since ice sanding usually provides a more uniform application. Ice sanding may also have less environmental impact because the water is usually held for sufficient time to allow silt-sized particles to settle out before water is discharged. Always release flood waters slowly.

## **XI. - NEIGHBOR TO NEIGHBOR RELATIONS**

U.S. Census data indicates people are leaving urban population centers for suburban and rural areas. Some people move to rural areas with certain expectations that conflict with agricultural practices. Several management practices listed here can be helpful in maintaining good relations with your neighbors.

**Keep your cranberry farm and adjoining property clean and free of debris.**

A clean and well managed cranberry operation demonstrates pride of ownership and portrays a high level of professionalism to outsiders, whether it be residential neighbors or regulatory agency personnel. If stockpiles of pipe, culverts, and equipment parts must be maintained, try to keep material orderly and not in view.

**Communication is the key to good neighbor relations.**

Effective communication with neighbors helps prevent and resolve problems. Inform neighbors about all aspects of cranberry production. Consider hosting tours around a social event or to observe harvest. This gives you the opportunity to explain cranberry growing firsthand. Once your neighbors have a better understanding of what you do, they may be more comfortable with your activities. It also gives you the opportunity to hear their concerns and develop positive relationships with them.

Explain to neighbors the importance of safe and ecologically-sound crop management practices, including IPM, pesticide use, and the importance of adhering to pesticide notices and sign posting. Be selective in crop management practices and evaluate the human and environmental risks associated with their use.

Be sensitive to concerns of neighbors. Be aware there are strong odors associated with certain pesticides. Post your property with appropriate signs prior to pesticide applications. Consider notifying neighbors before pesticide applications.

Much of the information in this document was derived from the Wisconsin State Cranberry Growers' Association, "Cranberry Grower Resource Notebook" of March, 1995, and "Standard Agricultural Practices for Cranberry Production in Wisconsin" of February, 1992.

## APPENDIX I. REFERENCES

### GENERAL CULTURE

- *Best Management Practices Guide for Massachusetts Cranberry Production* Bulletin 445. University of Massachusetts.
- *Cranberry Production in Wisconsin*. University of Wisconsin.
- *Cranberry Agriculture in Maine Grower's Guide*. Maine Dept. of Ag., Food & Rural Resources, Division of Production Development, State House Station 2.
- *Cranberry Grower Resource Notebook*. 1995. Wisconsin State Cranberry Growers Association.
- *Cranberry IPM Notebook*. University of Massachusetts.
- *Cranberry Production Guide, SP-127*. University of Massachusetts.
- *Cranberry Production in the Pacific Northwest*. Washington State University. PNW-27.
- *Michigan Fruit Management Guide*. Michigan State University Extension Bulletin No. 154.

### PEST AND DISEASE MANAGEMENT

- A field identification guide: Insect pests. University of Massachusetts.
- *Black Rot of Cranberry*. University of Wisconsin A3197.
- *Botryosphaeria Fruit Rot & Leaf Drop*. University of Wisconsin A3351.
- *Compendium of Blueberry and Cranberry Diseases*. The American Phytopathological Society. (1995).
- *Cranberry Fruit Rot Diseases in Wisconsin*. A3745. University of Wisconsin (2001).
- *Cranberry Insects of the Northeast*. University of Massachusetts.
- *Cranberry Insect, Disease & Weed Control Program*. Washington State University Bulletin EB845.
- *Cranberry Pest Management in Wisconsin*. University of Wisconsin A3276.
- *Cranberry Chart Book and Management Guide for Massachusetts*. University of Massachusetts. (Updated annually).
- *Cranberry Stem Gall*. A3795. University of Wisconsin (2004).
- *Early Rot (Scald) of Cranberry & Blast of Blossoms & Young Fruit*. University of Wisconsin A3352.
- *Fungal Leaf Spot Diseases of Cranberry in Wisconsin*. A3711. University of Wisconsin (1999).
- *Gibbera Leaf Spot & Berry Speckle of Cranberry*. University of Wisconsin A3193.
- *Hard Rot & Tip Blight of Cranberry*. University of Wisconsin A3194.
- *Insect Pests of Massachusetts Cranberry Bogs, A Field Identification Guide*, University of Massachusetts.
- *Major Cranberry Insect Pests IPM Fact Sheet*. University of Massachusetts.
- *Red Leaf Spot*. University of Wisconsin A3343.

- *The Blackheaded Fireworm IPM Fact Sheet.* University of Massachusetts.
- *The Cranberry Fruit Worm IPM Fact Sheet.* University of Massachusetts.
- *The Cranberry Girdler.* University of Wisconsin A3188.
- *The Cranberry Weevil IPM Fact Sheet.* University of Massachusetts.
- *The Southern Red Mite IPM Fact Sheet.* University of Massachusetts.
- *Viscid Rot & Upright Dieback of Cranberry.* University of Wisconsin A3195.
- *Yellow Rot of Cranberry.* University of Wisconsin A3350.

## **WATER AND NUTRIENT MANAGEMENT**

- *Cranberry Tissue Testing for Producing Beds in North America.* EM-8610. Oregon State University.
- *Fertilizer Guide, South Coastal Oregon Cranberries.* Oregon State University FG75
- *Fertilizer Guide, Irrigation Water Quality.* Oregon State University. FG76
- *Nitrogen in Bearing Cranberries in North America.* Oregon State University
- *Phosphorus for Bearing Cranberries in North America.* University of Wisconsin.
- *Sprinkler Irrigation Application Rates & Depths.* Washington State University Bulletin EB1305.

## **WEED MANAGEMENT**

- *Aquatic Vegetation Management & Control.* Washington State University PNW224.
- *Calibrating & Using a Backpack Sprayer.* Washington State University PNW320.
- *Control of Aster & Birdsfoot Trefoil in Cranberries with Napropamide.* Washington State University.
- *Cranberry Pest Control Weed Identification Series.* University of Wisconsin.
- *Cranberry Weed Control in Wisconsin.* University of Wisconsin A2226.
- *Field Guide to Common Weeds in Southeastern MA.* University of Massachusetts.

## **PESTICIDE USE AND REGULATIONS**

- *Chemical Applications in Agriculture, Methods and Equipment for Field Sprayers.* Michigan State University NCR 520.
- *FARM\*A\*SYST for Michigan Producers.* FAS-107. Michigan State University (2011)
- *SARA Title III, The Farmer's Responsibility Under the Emergency Planning and Community Right-To-Know Law.* Michigan State University E-2175.
- *Using Chemigation Safely and Effectively.* Michigan State University E-2099.

## **MISCELLANEOUS**

- *Conservation Practice Standards and Specifications.* USDA Natural Resources Conservation Service Technical Guide (available through local NRCS offices).
- *Right-To-Farm Generally Accepted Agricultural and Management Practices for*



Irrigation Water Use. Michigan Department of Agriculture & Rural Development, Right to Farm Program

- *Right-To-Farm Generally Accepted Agricultural and Management Practices for Nutrient Utilization.* Michigan Department of Agriculture & Rural Development, Right to Farm Program.
- *Right-To-Farm Generally Accepted Agricultural and Management Practices for Pesticide Utilization and Pest Control.* Michigan Department of Agriculture & Rural Development, Right to Farm Program.
- *Frost Protection Guide for Massachusetts Cranberries.* University of Massachusetts.

## TO ORDER REFERENCES

**Michigan Department of Agriculture & Rural Development, Right To Farm Program.**  
P.O. Box 30017, Lansing, Michigan 48909

**Michigan State University.** MSU Bulletin Office, 117 Central Services, MSU, East Lansing, MI 48824-1001 Phone: 517-353-6740.

[http://www.msue.msu.edu/portal/default.cfm?pageset\\_id=25744&page\\_id=25794&msue\\_portal\\_id=25643](http://www.msue.msu.edu/portal/default.cfm?pageset_id=25744&page_id=25794&msue_portal_id=25643)

**Oregon State University.** Agriculture Communications, Admin. Services A422, Corvallis, OR 97331. <http://extension.oregonstate.edu/catalog/>

**University of Massachusetts.** Cranberry Experiment Station, Glen Charlie Road, P.O. Box 569, East Wareham, MA 02538.

<http://www.umass.edu/cranberry/services/publications.shtml>

**University of Wisconsin.** Cooperative Extension Service, 630 Linden, Madison, WI 53706. <http://learningstore.uwex.edu/>

**Washington State University.** Long Beach Research & Extension Unit, Route 1, Box 570, Long Beach, WA 98631. <http://pubs.wsu.edu/cgi-bin/pubs/>

## **APPENDIX II. AGENCIES, PERMITS AND REGULATORY PROGRAMS**

### **AGENCIES**

Prospective cranberry growers should have a general knowledge of the programs and responsibilities of federal, state, and local agencies and their regulatory programs that may be involved in cranberry production and harvest activities. Prior to establishing a cranberry production site, producers should consult with the MDEQ Water Resources Division (WRD), and all other appropriate state and federal agencies to identify potential permit requirements. All required permits need to be obtained prior to initiation of any regulated activities, such as construction of cranberry beds and associated facilities.

### **STATE AGENCIES AND REGULATORY PROGRAMS**

**MICHIGAN DEPARTMENT OF AGRICULTURE & RURAL DEVELOPMENT (MDARD)** administers the Soil Survey Act, Conservation Districts Act, Michigan Right to Farm Act, Michigan Drain Code, Fertilizer and Pesticide Control Act, and others, and is responsible for assembling agricultural statistics and promoting agricultural development in Michigan. The MDARD is involved in a joint effort with the MDEQ and the Michigan Cranberry Council to ensure consistency regarding the administration of the Memorandum of Agreement (MOA) on Cranberry Production and Environmental Protection between the two departments. Landowners may contact the Environmental Stewardship Division, MDARD for information on development and operation of cranberry production facilities. One function or purpose of the MOA is to ensure that staff of both agencies receive clear guidance on how to make decisions relative to cranberry production in Michigan.

**MICHIGAN DEPARTMENT OF ENVIRONMENTAL QUALITY (MDEQ)** administers the state's regulatory programs involving wetlands, lakes, streams and similar water bodies and floodplains. The key MDEQ regulatory and permitting programs that may be involved with the production of cranberries are commonly referred to as Part 303 Wetlands Protection Part 301, Inland Lakes and Streams, and the Floodplain Regulatory Authority found in Part 31, Water Resources of the Natural Resources and Environmental Protection Act, PA 451 of 1994, as amended. The MDEQ also administers Section 404 of the Federal Clean Water Act in the non-coastal areas of Michigan through a Memorandum of Agreement with the U.S. EPA. Permit applications for work in regulated wetlands, lakes, streams or floodplains are submitted to the MDEQ's WRD.

**STATE WETLAND PERMIT PROGRAM.** The construction of commercial cranberry farm operations in Michigan will typically include activities that involve regulatory programs administered by the WRD. Part 303 requires that an individual obtain a state permit for work in any regulated wetland. Wetlands are defined as "land characterized by the presence of water at a frequency and duration sufficient to support, and that under normal circumstances does support, wetland vegetation or aquatic life and is commonly referred

to as a bog, swamp, or marsh, and which is any of the following:"

Contiguous to the Great Lakes or Lake St. Clair, an inland lake or pond, or a river or stream;

- Not contiguous to the Great Lakes, an inland lake or pond, or a river or stream; and more than 5 acres in size;

- Not contiguous to the Great Lakes, an inland lake or pond, or a river or stream; and 5 acres or less in size if the MDEQ determines that protection of the area is essential to the preservation of the natural resources of the state, from pollution, impairment, or destruction and the MDEQ has so notified the owner.

The term, "Contiguous" is further defined within the Part 303 Administrative Rules, as meaning any of the following:

- (i) A permanent surface water connection or other direct physical contact with an inland lake or pond, a river or stream, one of the Great Lakes, or Lake St. Clair.
- (ii) A seasonal or intermittent direct surface water connection to an inland lake or pond, a river or stream, one of the Great Lakes, or Lake St. Clair.
- (iii) A wetland is partially or entirely located within 500 feet of the ordinary high watermark of an inland lake or pond or a river or stream or is within 1,000 feet of the ordinary high watermark of one of the Great Lakes or Lake St. Clair, unless it is determined by the department, pursuant to R 281.924(5), that there is no surface water or groundwater connection to these waters.
- (iv) Two or more areas of wetland separated only by barriers, such as, dikes, roads, berms, or other similar features, but with any of the wetland areas contiguous under the criteria described in paragraph (i), (ii), or (iii) of this subdivision.

The connecting waters of the Great Lakes, including the St. Marys, St. Clair, and Detroit rivers, shall be considered part of the Great Lakes for purposes of this definition.

A state wetlands permit is required for any grading, filling, drainage, construction of dikes, ditches, or reservoirs, or placement of other structures within a regulated wetland. There is no fee for a pre-application assessment for cranberry production activities.

For a fee, the MDEQ has available a Wetland Identification Program (WIP) whereby a person can request the MDEQ to assess whether a parcel of property or portion of a parcel is wetlands and regulated under Part 303. The findings of the MDEQ under the WIP are guaranteed for a 3-year period. Application forms to request a WIP assessment can be obtained at:

[http://www.michigan.gov/deq/0,1607,7-135-3313\\_3687-10193--,00.html](http://www.michigan.gov/deq/0,1607,7-135-3313_3687-10193--,00.html)

County wetland inventory maps, which combine information from the Michigan Resources Inventory (MIRIS); United States Fish and Wildlife Service, National Wetland Inventory (NWI) maps; and the United States Department of Agriculture, Natural Resources Conservation Service, soil surveys, are available at the County Register of Deeds, the County Clerks office, or the County Extension Services offices. In addition, county wetland inventory maps and information regarding county wetland inventory maps are available at the following MDEQ website:

[http://www.michigan.gov/deq/0,1607,7-135-3313\\_3687-11178--,00.html](http://www.michigan.gov/deq/0,1607,7-135-3313_3687-11178--,00.html).

The National Wetland Inventory maps for Michigan are available at the U.S. Fish and Wildlife Service offices with county soil surveys available at USDA Natural Resources Conservation Service county offices. Although these sources may be helpful initially in identifying potential wetlands areas, the MDEQ has final authority for identifying regulated wetland areas based upon site visits.

**OTHER STATE REGULATORY PROGRAMS.** In addition to a wetland permit, Part 301 - Inland Lakes and Streams requires that an individual obtain a permit for construction of upland reservoirs, construction of stream crossings, construction activities in a water body to facilitate water withdrawal, placement of water control structures or for alteration of lakes and streams, as defined by the statute.

An individual planning a cranberry farm operation should be aware that in addition to construction permits that may be required under Part 301 and/or 303, additional construction permits may also be required from the WRD under the Floodplain Regulatory Authority (Part 31) and the provisions of Part 315, Dam Safety. In applying for state permits, the WRD requires the submittal of a single application form for permitting programs, administered by the WRD. A separate and different permit application form is required to be submitted to Wildlife Division, DNRE for impacts to a listed, threatened, or endangered species. In addition, depending on the operation of the cranberry facility, there may be water reporting requirements for withdrawal of water under provisions of the water use reporting authority of Part 327 NREPA.

Part 31, Water Resources protection of NREPA, Section 3109, states that: "A person shall not directly OR INDIRECTLY discharge into the waters of the state any substance that is OR MAY BECOME injurious to any of the following: (a) to the public health, safety, or welfare. (b) to domestic, commercial, industrial, agricultural, recreational, or other uses that are being made or may be made of such waters. (c) to the value or utility of riparian lands. (d) to livestock, wild animals, birds, fish, aquatic life, or plants or to their growth or propagation thereof be prevented or injuriously affected; or whereby (e) to the value of fish and game. (Emphasis added)

Part 31 defines "Waters of the state" as groundwaters, lakes, rivers, and streams and all other watercourses and waters within the jurisdiction of the state and also the Great Lakes

bordering the state. Additional state permits may be required for discharges to surface waters of the state. The property owner and/or producer should check with the WRD to identify potential permit requirements for discharges to waters of the state.

**LOCAL APPROVAL.** If a project involves a change to or use of a designated county drain, the producer should check for necessary approvals from the county drain office.

**THE MICHIGAN RIGHT TO FARM ACT**, PA 93 of 1981, as amended, cites the following MCL 286.473, Sec. 3 (3): "A farm or farm operation that is in conformance with subsection (1) shall not be found to be a public or private nuisance as a result of any of the following:

- (a) A change in ownership or size.
- (b) Temporary cessation or interruption of farming.
- (c) Enrollment in governmental programs.
- (d) Adoption of new technology.
- (e) A change in type of farm product being produced."

## **FEDERAL AGENCIES AND REGULATORY PROGRAMS**

**UNITED STATES ARMY CORPS OF ENGINEERS (COE)** is the permitting authority for Section 404 of the Clean Water Act, except as modified by the Michigan's administration of the Federal Section 404 Program.

**ENVIRONMENTAL PROTECTION AGENCY (EPA)** has veto authority over the COE decisions and is the lead agency for the Clean Water Act.

**FEDERAL SECTION 404 PERMIT PROGRAM.** In addition to the state permit requirements under Michigan's regulatory programs, Section 404 of the Federal Clean Water Act regulates placement of fill and dredge materials in waters of the United States, including wetlands. In most states, a permit must be obtained from the COE for dredge and fill activities that would result in the placement or redistribution of material in wetlands and waters of the United States. In 1984, the U.S. Environmental Protection Agency (EPA) authorized Michigan to administer the Federal Section 404 program in most areas of Michigan. In those areas where Michigan has Section 404 authority, a state issued inland lakes and streams or wetland permit also authorizes activity under the Federal Clean Water Act. Michigan's Section 404 program is required to meet Federal Clean Water Act standards as long as Michigan administers the federal permit program. Action taken under the state-assumed Section 404 program is a state action taken under state law, not a federal action. The MDEQ may not issue a permit that carries Section 404 authority if the EPA objects to the project.

The COE has retained Section 404 jurisdiction over traditionally navigable waters including the Great Lakes, connecting channels, and other waters connected to the Great Lakes where navigational concerns are maintained. The COE also retained Section 404 jurisdiction in wetlands directly adjacent to these waters. Therefore, in Great Lakes

coastal areas and adjacent wetlands, both state and federal permits are required for dredge and fill activities within wetlands and surface waters. To avoid confusion to the permit applicant, the Detroit District COE and MDEQ provide a joint application process that utilizes the same application form. The application is submitted to MDEQ, which forwards copies of the application to the COE if there is separate federal jurisdiction. Application forms and additional information on materials to submit with the application for a proposed cranberry farm operation can be obtained from the WRD, MDEQ at:

[http://www.michigan.gov/deq/0,1607,7-135-3313\\_3687-10813--,00.html](http://www.michigan.gov/deq/0,1607,7-135-3313_3687-10813--,00.html).

**U.S. DEPARTMENT OF INTERIOR, FISH AND WILDLIFE SERVICE (FWS)** has an advisory role in the permitting process and mitigation decisions.

**U.S. DEPARTMENT OF AGRICULTURE (USDA):** Three USDA agencies may be helpful with cranberry production issues. The Natural Resources Conservation Service (NRCS) is the lead agency for soil surveys and soil information, such as prime, unique and important agricultural land. NRCS also provides highly erodible land and wetland determinations for purposes of USDA program eligibility. NRCS also provides direct technical assistance to landowners to develop and implement their conservation plans. The Farm Service Agency (FSA) is responsible for providing, filing, and maintaining the official copy of the land determinations provided by the NRCS. FSA uses this and other information to identify farms and land areas suitable for different uses. FSA also provides loans and grants as per farm bills and farm programs. Rural Development (RD) is responsible for providing financial assistance to rural businesses and both financial and technical assistance to cooperatives. RD may consider the market value of brand names, patents, or trademarks.

## **THE FEDERAL FARM BILL**

The 1935 Farm Bill is an Act to provide protection of land resources from soil erosion and sedimentation, and also protect water resources. In 1977, USDA's OGC reinterpreted the 1940 Presidential reorganization, permitting the Soil Conservation Service, presently the NRCS, to work on tribal lands situated within boundaries of a conservation district. In 1980, the USDA extended conservation assistance to Indians on tribal lands. The 1985 Farm Bill (Food Security Act of 1985), as amended by the 1990 Farm Bill (Food, Agriculture, Conservation and Trade Act of 1990), the 1996 Farm Bill (Federal Agriculture Improvement and Reform Act of 1996), the 2002 Farm Bill (Farm Security and Rural Investment Act of 2002) and the 2008 Farm Bill (Food, Conservation and Energy Act of 2008), addresses producer eligibility for USDA programs such as the Conservation Security Program (CSP).

Proposed cranberry production on existing wetlands will be exempted for USDA program benefit eligibility as a Manipulated Wetland (Wx). This exemption will require that a Wx plan be developed and filed with the Natural Resources Conservation Service (NRCS). An application for an exemption must be submitted to and approved by the local NRCS office before conversion activities begin. The area will then be labeled Wx and recorded on the

USDA Farm Services Agency aerial photography.

Cranberry production is allowed on prior converted wetlands as defined in USDA Farm Bill legislation. Prior converted croplands (PC) are wetlands that were drained, dredged, filled, leveled, or otherwise manipulated, including the removal of woody vegetation, before December 23, 1985, for the purpose of, or to have the effect of, making the production of an agricultural commodity possible, and an agricultural commodity was planted or produced at least once prior to December 23, 1985. Prior converted croplands converted before December 23, 1985, are exempt from Farm Bill Swampbuster provisions and may not be considered to be waters of the United States subject to regulatory jurisdiction under Section 404 of the Clean Water Act. Certified wetland determinations made by NRCS and accepted by the Corp of Engineers for Clean Water Act purposes will be considered valid by the Corps for five years.

## **APPENDIX III. CRANBERRY SITE REQUIREMENTS**

The three basic considerations in choosing a suitable cranberry site are climate, soils, and water. These items will be addressed separately, although they are related to some degree. The climatic considerations can be discussed on a regional basis. However, the suitability of a specific location is based primarily on the soil and water characteristics. Since these characteristics are very site specific, we will discuss soil and water requirements in a general sense.

### **Climate**

The American cranberry is native to Maine and Nova Scotia, west to Minnesota, and as far south as Virginia and Tennessee. This represents a wide range of climatic conditions. Commercial production areas also vary enormously from the moderated marine climates of western Oregon and Washington to the harsh continental climate of central and northern Wisconsin. The suitability of Michigan regions for cranberry production can be assessed by comparing the climate to perhaps the harshest production area, Wisconsin.

There is little doubt that most of Michigan offers suitable climate. Cranberries have been successfully grown experimentally and commercially in the severe conditions of the U.P. In most respects, the climate in southern Michigan is less challenging.

### **Minimum Winter Temperatures**

Cranberry leaves and buds are subject to cold injury during the winter. Generally, midwinter temperatures below 10°F will injure plants and higher temperatures may cause injury if accompanied by wind. Since these temperatures are common in Wisconsin, Massachusetts and New Jersey, bogs in these states are typically covered during the winter with a protective layer of ice.

The USDA Hardiness Zones reflect primarily average minimum winter temperatures. Cranberry production regions range from Zone 3 (northern Wisconsin) to Zone 9 (Pacific Northwest). Michigan falls between these extremes (Zone 4 in the Western U.P. to Zone 6 in Southwest Lower Michigan).

The fact that Michigan winters are more moderate than those in Wisconsin, presents some questions about winter protection. Wisconsin growers are able to maintain ice on beds throughout the winter. Southern Michigan frequently experiences "winter thaws", when ice cover would likely be lost. Beds would periodically need to be re-flooded to form new ice. Southwest Michigan also receives more snow than production areas of Wisconsin, which could impede ice formation and cause oxygen shortages beneath the ice. Growers in this area may need to develop winter protection strategies more similar to those in Massachusetts or New Jersey than Wisconsin.



## **Soils**

Most traditional cranberry sites are on two general soil types - acid organic soils or poorly drained mineral soils. The properties of these soils include a pH of 3.5 to 5.0 in the surface and a water table at six to 12 inches during the growing season. These traditional sites are easily converted and have adequate water. The disadvantage of these soils is that they are wetlands with surface water systems, and their development requires permitting. The following characteristics of traditional cranberry sites are fundamental plant requirements:

1. Surface Texture - usually a peat or muck organic soil surface or sandy mineral soil.
2. Depth - greater than 40 inches to bedrock.
3. Slope - zero to two percent.
4. Water Table - ranges from 1.5 to 3.0 feet during the growing season (generally poorly drained or very poorly drained soils).
5. Reaction - surface horizon pH of 4.0 to 5.5.

Some cranberry operations have recently been developed by modifying non-traditional sites so that the basic requirements above are met. This approach has been taken to avoid wetland and water use regulations, and because these sites are readily available in some areas. Other non-traditional soils have been proposed for cranberries, but they have not been tested. It is important to recognize that although several basic non-traditional sites have been proposed, the basic requirements listed above need to be met in order to successfully produce cranberries. This may require significant additional development costs. We have categorized non-traditional sites into two alternatives:

### **Somewhat poorly drained and moderately well drained sands with regional water tables.**

These soils have sandy surfaces with varying amounts of organic matter, pH of 4.0 to 5.5 in the surface, and water tables one to three feet (somewhat poorly drained) to 2.5 to 6.0 feet (moderately well drained) during the growing season.

An advantage of these soils is that they are not typically classified as wetlands. The major disadvantage is their high permeability, which could lead to problems maintaining desired water table levels or with movement of chemicals into groundwater. Several existing cranberry operations in Wisconsin have expanded into these upland sites.

## Water

Cranberry production requires large amounts of water. Water is needed to protect plants against frost damage in the spring and fall. Traditionally, plantings were flooded before predicted frosts. Most growers now frost protect by sprinkling water on plants, since this requires much less water than flooding. Irrigation is also needed throughout the growing season to meet the water demands of the plants. Cranberry plants are shallow rooted and desiccate easily. Sprinkler systems may also be used to cool the plants during hot summer weather. Beds that are wet harvested are flooded in October with one foot of water to remove the berries, and a second one foot flood may be used to remove trash from the bed. Beds are again flooded with one foot of water in the winter to protect plants from winter weather.

Actual water requirements vary with location and management practices, and are often expressed in acre-feet. One acre-foot is the water needed to cover an acre to a depth of one foot (about 330,000 gallons). Water use estimates range from 5.1 acre-feet in Maine, to 6 acre-feet in Wisconsin, and 7.8 acre-feet in Massachusetts. However, if beds and reservoirs are designed to recycle water, actual water use may be as little as 1.5 acre feet. This system would require impervious soil substrata to prevent deep seepage losses of water, and a topographical layout that allows cycling of water from one bed to another and from beds to reservoirs.

| Seasonal Water Need Estimates (acre-feet) for Cranberries                                                                                                                                  |                                  |                    |                            |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------|--------------------|----------------------------|
| Time                                                                                                                                                                                       | Use                              | Maine <sup>1</sup> | Massachusetts <sup>2</sup> |
| April – May                                                                                                                                                                                | Spring frost protection          | 0.5                | 1.7                        |
| June - August                                                                                                                                                                              | Irrigation, cooling, chemigation | 1.2                | 1.1                        |
| September - October                                                                                                                                                                        | Fall frost protection            | 0.4                |                            |
| October                                                                                                                                                                                    | Harvest flood                    | 1.0                | 2.0                        |
| October - November                                                                                                                                                                         | De-trash flood                   | 1.0                |                            |
| December                                                                                                                                                                                   | Winter flood                     | 1.0                | 2.0                        |
| Winter                                                                                                                                                                                     | 2 <sup>nd</sup> Winter flood     |                    | 1.0                        |
|                                                                                                                                                                                            | <b>Annual Total</b>              | <b>5.1</b>         | <b>7.8</b>                 |
| <sup>1</sup> Cranberry Agriculture in Maine Grower's Guide. Maine Cranberry Development Comm., 1993<br><sup>2</sup> Massachusetts Cranberry Production. Univ. Mass. Coop. Ext. Serv., 1993 |                                  |                    |                            |

Acquiring and discharging water are prime concerns in selecting cranberry sites. Cranberry operations typically use surface water from existing sources (lakes, streams, drainage ditches) or from reservoirs. Access to water from lakes or streams may require permits. Construction of reservoirs of sufficient size may also require permits if they are located on existing wetlands. Wells typically do not have the capacity to supply the large volumes of water required at specific times. Well water may also be difficult to use for winter floods because it requires more time to cool and freeze. Wells can be used to replenish smaller reservoirs.

In addition, relatively large volumes of water may be discharged to drainage ditches, streams or lakes. Discharge may also require permits, since the temperature and chemistry of receiving waters can be affected.

### **Agricultural Water Use Reporting**

Water use reporting is one of the tools that Michigan uses to catalogue water use for the protection of the state's water resources from diversions to other regions of the country, and to improve Michigan's stewardship of this precious resource. The original legislation, now Part 327 of NREPA was signed into law in 2003. Michigan law requires that all new or increased large quantity water withdrawals (groundwater or surface water) use the Michigan Water Withdrawal Assessment Tool, to register an acceptable water withdrawal, or seek a site specific review from the MDEQ to determine whether a proposed large quantity withdrawal will cause an "adverse resource impact". A large quantity withdrawal (LQW) is defined as one with a pump capacity that exceeds 100,000 gallons per day or greater from all sources (excluding residential use) under common ownership or farm as defined by the Michigan Right to Farm Act. Once a large quantity water withdrawal is registered with the state, the operator is required to continue to report their water use on a yearly basis to the MDARD. For access to the Michigan Water Withdrawal Assessment Tool and information on water use reporting or registering a new withdrawal go to:

[http://www.michigan.gov/deq/0,1607,7-135-3313\\_3684\\_45331---,00.html](http://www.michigan.gov/deq/0,1607,7-135-3313_3684_45331---,00.html)

### **Spring and Autumn Frost Potential**

The average time between the last killing spring frost and the first killing fall frost defines the growing season. In natural environments, cranberries need about 150 frost free days to mature the berry crop. The growing season in cranberry production areas is longest in Oregon and Washington (280 days) and shortest in Wisconsin (110 days in some northern areas and 160 days in the south). The growing season in Michigan ranges from 100 days in the western U.P. to 170 days in southwest Lower Michigan. Cranberry growers protect against frosts and extend the effective growing season by sprinkle irrigating or flooding. However, production in short season areas will require more frequent frost protection and thus greater management costs.

### **Precipitation/Evapo-transpiration: Irrigation Requirements.**

Irrigation requirements are dependent on the amount of precipitation and evapo-transpiration or amount of water lost to the air from leaves and the soil surface. Annual precipitation in major production areas ranges from 30 inches in Wisconsin to 80 inches in parts of Oregon and Washington. Average annual precipitation in Michigan ranges from 28 inches in parts of the U.P. to 36 inches in southern Michigan. Warm-season precipitation (April-September) provides an indication of the need for supplemental irrigation during the growing season. Production areas in Wisconsin receive 20 to 22 inches between April and September, whereas warm-season totals for Michigan range from 16 to 22 inches. The lowest April to September totals in Michigan (16 inches) occur in the eastern U.P. and the extreme northern portion of the Lower Peninsula.

The evapo-transpiration from cranberry bogs in Michigan would likely be similar to bogs in Wisconsin. Air temperatures and relative humidity, which largely control evapo-transpiration, are generally similar in Wisconsin and Michigan. Because water losses through evapo-transpiration and precipitation are similar, irrigation requirements are generally expected to be similar between the two states.

Sprinklers are also used to cool cranberry plants during very warm days. High temperatures or dry winds early in the season may cause new growth to desiccate and "blast", whereas hot weather later in the season may cause scalding of the berries. Temperatures as low as 80°F can injure plants in the normally cool Pacific Northwest, whereas 85°F may cause injury under New Jersey conditions. Plantings in Michigan may require less water for cooling than plantings at similar latitudes in Wisconsin.

### **Heat Units and Growing Degree Days**

Temperatures during the growing season may have affected the growth of cranberry plants and fruit differently. Optimum temperatures appear to be 60 to 80°F. Lower temperatures may limit yields by slowing growth and berry development. Higher temperatures can cause sun burning of berries during the summer, and inhibit color development if occurring during the fall. Growing degree days (GDD) are a measure of the heat accumulation during the season. Production areas in Wisconsin usually accumulate 2500 (north-central areas) to 3000 (central) GDD base 45°F. The U. P. of Michigan typically accumulates 2300-2500 GDD base 45°F, and extreme southern Michigan sees up to 3800 GDD. On average, GDDs in the U.P. are slightly lower than those in even the cooler production areas of Wisconsin, and the GDDs in southern Michigan are comparable to those in southern Wisconsin.

## APPENDIX IV. WATER BUDGET DATA SHEET

This worksheet addresses questions that should be considered for proposed cranberry sites. Each cranberry operation is unique in regard to the source of water, layout, etc., so only consider those questions that pertain to your operation (i.e., if your cranberry operation has a river as its water source, answer the questions under River/Stream and not those under Groundwater and Lake). Calculations, assumptions and sources of information should be retained.

### I. DESCRIBE YOUR WATER SOURCE(S)

#### A. River/Stream

1. Use gauging data if available; if not available, provide best calculations based on drainage area, land use, etc., or data from a similar stream and watershed located as near as possible to the project site.

Average annual flow in cubic feet per second (cfs)

CFS flow and elevation for 100-year flood event

7Q10 flow (lowest 7-day flow in 10-year period)

7Q2 flow (lowest 7-day flow in a 2-year period)

Quantify the anticipated stream diversion, cfs /day, number of days.

2. Provide a map (to scale, 1"= 1,000') showing that portion of the project area within the 100-year floodplain and/or floodway.
3. Provide a cross-sectional drawing of the stream, upstream and downstream of the operation, showing water level at average annual flow and at 7Q2 and 7Q10.

#### B. Lake/Reservoir

1. Describe the surface elevation, surface acreage and acre-feet (AF) of storage of the lake/reservoir during average, high water, and drought conditions.
2. Is the lake/reservoir isolated or connected to other lakes and/or river systems? Describe. Provide map as appropriate.

#### C. Watershed Information

1. Size (acres or square miles).
2. Average slope of watershed.

3. Characterize soils of the watershed (percent peat, percent sand, percent clay, percent impervious surfaces, etc.) using the county soil survey (if none has been prepared for your county, provide best available information).
4. Characterize watershed land use (percent in upland forest, wetland, lakes, cranberry reservoirs, cranberry beds, other agriculture, urban, etc.)
5. If there are existing cranberry reservoir(s) on site, describe the distance from the project area, surface elevation, surface area, and AF of storage capacity during:
  - a. Average conditions.
  - b. High water conditions.
  - c. Drought conditions (e.g. 1976 and 1988).

#### **D. Groundwater**

1. Average depth to water table.
2. Describe springs and seeps (e.g. number, location, estimated flow (in gallons per minute [gpm], etc.)
3. Describe the permeability rate of the soil(s) involved at your site (refer to county soil survey information).
4. If reservoirs are to be constructed or enhanced, include the permeability rate of soils in the area. If a county soil survey is not available, take representative core samples to estimate permeability using methods similar to those utilized in soil surveys.
5. Identify wetlands that may be drained as a result of groundwater removal.

## **II: DESCRIBE HOW YOUR WATER SUPPLY SYSTEM WOULD WORK**

- A. What is the total water supply (in AF) combining river/stream, lake/reservoir and/or groundwater sources? What percentage would each contribute to your water supply?
- B. If the proposal is an expansion of an existing cranberry operation, describe how the proposed expansion would tie in.
- C. Identify discharge points on the site plan and for each indicate the frequency, duration, and volume. (If more than one point, give percentages for each):
  1. Reservoir(s) - (Give estimated detention time for reservoirs used as temporary detention basins.)

2. Natural lake.
3. Stream/river.
4. Wetland complex.

### **III. WATER USE**

Precipitation, evapo-transpiration, and runoff amounts vary throughout Michigan. Data for specific locations can be obtained from the State Climatologists Office, Room 417, Natural Science Building, Michigan State University, East Lansing, MI 48824, 517-355-0231. the average annual water use for cranberry production is 6 AF per acre of bed. Average annual precipitation ranges from 28 to 36 inches, and runoff from 6 to 21 inches.

- A. Water requirements of your cranberry operation (acres of beds x 6 AF), both proposed and existing (if applicable)\_\_\_\_\_.
- B. Estimate, in AF and percentage of total water use, how much water would be reused (i.e., pumped back into reservoir), during what time period.
- C. Estimate how much water would be lost due to seepage.
- D. Estimate AF of water discharged from the cranberry operation (i.e., to river or lake).
- E. Complete a balance sheet of water sources (river, lake, reservoir, groundwater, net precipitation, etc.) and water uses (6 AF per bed, seepage, discharged outside of cranberry operation, etc.) for a one year period assuming average conditions.

### **IV. IMPACT ANALYSIS**

Prior to completing the following elements, the owner and/or operator is required to run the online MDEQ Water Withdrawal Assessment Tool to determine if the withdrawal, as proposed, withdrawal is acceptable or requires a site specific review by MDEQ to determine if there is sufficient water available or if the proposed use will result in an adverse resource impact.

#### **A. River/Stream Water Source**

1. Provide a water quantity analysis evaluating the in-stream impacts, both upstream and downstream, of withdrawing water for your cranberry operation.
2. Under a worst case situation, such as the drought of 1976 or 1988, what percent of the cfs flow of the river/stream would be diverted to your cranberry operation?

Use cross-sectional drawings similar to those in Part I.A.3. to show downstream water levels under average conditions and at 7Q2 with the proposed project in place.

### **B. Lake/Reservoir Water Source**

1. How much would the surface elevation be lowered during the maximum short-term withdrawal (e.g. putting on the winter flood)?
2. If a reservoir (impoundment) is used, what is the distance and difference in elevation to the nearest occupied buildings located downstream and laterally (adjacent to the reservoir) considering both on your property and neighboring properties?

### **C. Groundwater Water Source**

Describe the effect on the groundwater elevation due to proposed dikes, reservoirs, etc. (e.g. would the proposed reservoir raise the groundwater elevation? If so, how much?)

### **D. Summary**

Describe how your water use could affect neighboring property owners (both upstream and downstream), wildlife refuges, recreational areas, public or private water supplies, other cranberry operations, and/or other agricultural users.



## Review Committee

Dr. Eric Hanson  
Department of Horticulture  
Michigan State University  
East Lansing, MI 48824  
Voice: (517) 355-5191, Ext. 386  
FAX: (517) 353-0890  
E-mail:[hansone@msu.edu](mailto:hansone@msu.edu)

Tom Allenson  
U.S. Army Corps of Engineers  
Detroit District  
P.O. Box 1027  
Detroit, MI 48231  
Voice: (313) 226-2221  
FAX: (313) 226-6763  
E-mail:[Thomas.E.Allenson@usace.army.mil](mailto:Thomas.E.Allenson@usace.army.mil)

Mike DeGrandchamp  
Michigan Cranberry Council  
15575 77<sup>th</sup> Street  
South Haven, MI 49090  
Voice: (269) 637-3915  
FAX: (269) 637-2531  
E-mail:[mike@degranchamps.com](mailto:mike@degranchamps.com)

Betsy Dierberger  
USDA-NRCS  
3001 Coolidge Road, Suite 250  
East Lansing, MI 48823-6321  
Voice: (517) 324-5265  
FAX: (517) 324-5171  
E-mail:[betsy.dierberger@mi.usda.gov](mailto:betsy.dierberger@mi.usda.gov)

Erik Johnson  
Michigan Department of Agriculture & Rural  
Development  
513 Oak Street  
Manistee, MI 49660  
Voice: (231) 357-4323  
E-mail:[johnsone9@michigan.gov](mailto:johnsone9@michigan.gov)

Dr. William Larsen  
Michigan Department of Environmental Quality  
P.O. Box 30458  
Lansing, MI 48909  
Voice: (517) 373-9249  
FAX: (517) 241-8098  
E-mail:[larsenb@michigan.gov](mailto:larsenb@michigan.gov)

Mark Longstroth  
MSU Extension  
810 Hazen Street  
Paw Paw, MI 49079  
Voice: (616) 657-7745  
E-mail:[longstr7@msu.edu](mailto:longstr7@msu.edu)

Ken Nye  
Michigan Farm Bureau  
7373 West Saginaw Highway  
Lansing, MI 48909  
Voice: (517)323-7000, Ext. 2020  
FAX: (517) 323-0230  
E-mail:[knye@michfb.com](mailto:knye@michfb.com)